

Identity Platform provides Admin APIs to manage your tenants, users, and authentication tokens. You can leverage [Cloud Identity and Access Management \(/iam/\)](/iam/) to prevent unwanted access using these APIs.

Follow these steps to grant a user a role on a tenant resource:

1. Open the Identity Platform Tenants page in the Cloud Console.

[Go to the tenants page \(https://console.cloud.google.com/customer-identity/tenants\)](https://console.cloud.google.com/customer-identity/tenants)

2. Select a tenant from the list.
3. Switch to the **Permissions** tab in the info panel on the right.

The screenshot displays the 'Configure tenants connected to this project' interface. On the left, a table lists tenants with columns for 'Tenant', 'Tenant ID', and 'Enabled'. The 'MySecondTenant' is selected. On the right, the 'Tenant details' panel is open to the 'PERMISSIONS' tab, showing an 'ADD MEMBER' button and a list of roles: Editor (4), Firebase Admin SDK Administrator Service Agent (1), and Owner (3).

Tenant	Tenant ID	Enabled
MyFirstTenant	MyFirstTenant-9aob5	<input type="checkbox"/>
MySecondTenant	MySecondTenant-glr1	<input checked="" type="checkbox"/>

Tenant details

DETAILS **PERMISSIONS**

Edit or delete permissions below or 'Add Member' to grant new

Show inherited permissions

Filter tree

Role / Member ↑	Inheritance
▶ Editor (4)	
▶ Firebase Admin SDK Administrator Service Agent (1)	
▶ Owner (3)	

4. Click **Add member** to grant a user a new role, or use the list below to modify or revoke access for an existing user.

To learn more about access control using Cloud IAM, see the [Cloud IAM documentation \(/iam/docs/\)](/iam/docs/).

This table lists the role required to call each method in the Identity Platform API. The role should be assigned on the tenant resource.

Service	Method	Role
google.cloud.identitytoolkit.v1. AccountManagementService	GetOobCode	Editor
	SetAccountInfo	Editor
	UploadAccount	Editor
	DeleteAccount	Editor
	DownloadAccount	Viewer
	GetAccountInfo	Viewer
	QueryUserInfo	Viewer
google.cloud.identitytoolkit.v1. AuthenticationService	SignUp	Editor
google.cloud.identitytoolkit.v2. ProjectConfigService	CreateDefaultSupportedIdpConfig	Editor
	CreateInboundSamlConfig	Editor
	CreateOAuthIdpConfig	Editor
	CreateOutboundSamlConfig	Editor
	DeleteDefaultSupportedIdpConfig	Editor
	DeleteInboundSamlConfig	Editor
	DeleteOAuthIdpConfig	Editor
	DeleteOutboundSamlConfig	Editor
	GetDefaultSupportedIdpConfig	Viewer
	GetInboundSamlConfig	Viewer
	GetOAuthIdpConfig	Viewer
	GetOutboundSamlConfig	Viewer
ListDefaultSupportedIdpConfigs	Viewer	

Service	Method	Role
	ListInboundSamlConfigs	Viewer
	ListOAuthIdpConfigs	Viewer
	ListOutboundSamlConfigs	Viewer
	UpdateDefaultSupportedIdpConfigEditor	
	UpdateInboundSamlConfig	Editor
	UpdateOAuthIdpConfig	Editor
	UpdateOutboundSamlConfig	Editor
<b>google.cloud.identitytoolkit.v2.TenantManagementService</b>	CreateTenant	Editor (on the parent project)
	DeleteTenant	Editor
	UpdateTenant	Editor
	GetTenant	Viewer
	ListTenants	Viewer (on the parent project)